

<http://ned.ca/mentor-manager/>

A. Create Mentor roles: (mentor-system and mentor-user)

Step 1: Download role presets:

- Download and unpack this file: <http://ned.ca/mentor-roles-presets/mentor-roles.zip>. This file contains the role presets for mentor-user and mentor-system.

Step 2: Create Mentor-System role

- Go to Site Administration > Users > Permissions > Define Roles
- Click on the “Add a new role” button
- Click on “Choose a file” button next to the “User role preset” section, as shown here: <http://screencast.com/t/cM5QK5UZqPn0>
- Import the file mentor-system.xml and save the role

Step 3: Create Mentor-User role

- Repeat step 2 except time user the mentor-user.xml file

Alternatively, if you want to create these roles manually, adjust permissions or assign them to an existing role, here is a breakdown of each role. Otherwise, you may proceed to [Part B](#).

Mentor-User:

- Shortname: **mentor-user**
- Custom Full name: **Mentor User**
- Context types where this role may be assigned: **user**
- Set the following role capabilities to “Allow”:

<ul style="list-style-type: none"> ○ block/fn_mentor:viewcoursenotes ○ block/fn_mentor:viewactivitylist ○ block/fn_mentor:viewblock ○ mod/assign:grade ○ mod/assign:view ○ mod/assignment:grade ○ mod/assignment:view ○ moodle/user:readuserblogs ○ moodle/user:readuserposts ○ moodle/user:viewuseractivitiesreport ○ moodle/user:viewdetails 	<ul style="list-style-type: none"> ○ gradereport/user:view ○ moodle/grade:viewall ○ gradereport/grader:view ○ moodle/user:viewalldetails ○ moodle/grade:view ○ report/outline:view ○ report/progress:view ○ moodle/notes:view ○ moodle/notes:manage ○ block/fn_mentor:viewcoursenotese
---	--


Mentor-System:

- Shortname: **mentor-system**
- Custom Full name: **Mentor System**
- Context types where this role may be assigned: **system**
- Set the following role capabilities to “Allow”

- moodle/notes:view
- moodle/user:viewdetails
- block/fn_mentor:viewcoursenotes

B. Set up profile fields for mobile phone details:

To receive mobile text messages, a user must be associated with a cell number and a cell provider. This is defined in the user profile, as shown here:



Other fields

Cell number

Cell provider

Following the following two steps to create these profile fields:

Step 1: Go to *Site Administration > Users > Accounts > User Profile Fields* and create a new “**Text**” profile field with following details:

- Shortname: **mobilephone**
- Name: **Cell Phone** (or whatever you feel appropriate)
- Required: **no**
- Display on signup: **yes**
- Who is the field visible to: visible to user
- Display size: **10**
- Display length: **10**

Step 2: Create another profile field except this time select the “**Dropdown menu**” type. Use the following details:

- Shortname: **mobileprovider**
- Name: **Cell Provider** (or whatever you feel appropriate)
- Required: **no**
- Display on signup: **yes**
- Who is the field visible to: **Visible to user**
- Menu options: (This list contains most carriers for Canada and USA. Copy and paste the ones you need to cover your region.)

<p>3 River Wireless ~@sms.3rivers.net~ ACS Wireless ~@paging.acswireless.com~ Alltel ~@message.alltel.com~ AT&T ~@txt.att.net~ Bell Canada ~@txt.bellmobility.ca~ Bell Canada ~@bellmobility.ca~ Bell Mobility ~@txt.bellmobility.ca~ Bell Mobility (Canada) ~@txt.bell.ca~ Blue Sky Frog ~@blueskyfrog.com~ Bluegrass Cellular ~@sms.bluecell.com~ Boost Mobile ~@myboostmobile.com~ BPL Mobile ~@bplmobile.com~ Carolina West Wireless ~@cwwsms.com~ Cellular One ~@mobile.celloneusa.com~ Cellular South ~@csouth1.com~ Centennial Wireless ~@cwemail.com~ CenturyTel ~@messaging.centurytel.net~ Cingular (Now AT&T) ~@txt.att.net~ Clearnet ~@msg.clearnet.com~ Comcast ~@comcastpcs.textmsg.com~ Corr Wireless Communications ~@corrwireless.net~ Dobson ~@mobile.dobson.net~ Edge Wireless ~@sms.edgewireless.com~ Fido ~@fido.ca~ Golden Telecom ~@sms.goldentele.com~ Helio ~@messaging.sprintpcs.com~ Houston Cellular ~@text.houstoncellular.net~ Idea Cellular ~@ideacellular.net~ Illinois Valley Cellular ~@ivctext.com~ Inland Cellular Telephone ~@inlandlink.com~ MCI ~@pagemci.com~ Metro PCS ~@mymetropcs.com~</p>	<p>Metrocall ~@page.metrocall.com~ Metrocall 2-way ~@my2way.com~ Microcell ~@fido.ca~ Midwest Wireless ~@clearlydigital.com~ Mobilcomm ~@mobilecomm.net~ MTS ~@text.mtsmobility.com~ Nextel ~@messaging.nextel.com~ OnlineBeep ~@onlinebeep.net~ PCS One ~@pcsone.net~ President's Choice ~@txt.bell.ca~ Public Service Cellular ~@sms.pscel.com~ Qwest ~@qwestmp.com~ Rogers AT&T Wireless ~@pcs.rogers.com~ Rogers Canada ~@pcs.rogers.com~ Satellink ~.pageme@satellink.net~ Solo Mobile ~@txt.bell.ca~ Southwestern Bell ~@email.swbw.com~ Sprint ~@messaging.sprintpcs.com~ Sumcom ~@tms.suncom.com~ Surewest Communicaitons ~@mobile.surewest.com~ Telus ~@msg.telus.com~ Telus ~@msg.telus.com~ T-Mobile ~@tmomail.net~ Tracfone ~@txt.att.net~ Triton ~@tms.suncom.com~ Unicel ~@utext.com~ US Cellular ~@email.uscc.net~ US West ~@uswestdatamail.com~ Verizon ~@vtext.com~ Virgin Mobile ~@vmobl.com~ Virgin Mobile Canada ~@vmobile.ca~ West Central Wireless ~@sms.wcc.net~ Western Wireless ~@cellularonewest.com~</p>
---	---

- Default value: **Please select your cell provider**

C. Configure the plugin

- Change the block configuration page as needed. Make sure to include these key settings:

NED Mentor Manager

Block name	<input type="text" value="Mentor Manager"/>	Default: Mentor Manager
Page layout	<input type="text" value="login"/>	Default: login
Word for Mentor	<input type="text" value="Mentor"/>	Default: Mentor
Word for Mentors	<input type="text" value="Mentors"/>	Default: Mentors
Word for Mentee	<input type="text" value="Mentee"/>	Default: Mentee
Word for Mentees	<input type="text" value="Mentees"/>	Default: Mentees
Allow mentee to see block	<input type="checkbox"/>	Default: No
Student role	<input type="text" value="student"/>	Default: student
Teacher role	<input type="text" value="editingteacher"/>	Default: editingteacher
Mentor role - Sytem	<input type="text" value="mentor-system"/>	
Mentor role - User	<input type="text" value="mentor-user"/>	
Max number of mentees	<input type="text" value="15"/>	Default: 15
Allow mentor to see Notes	<input type="checkbox"/>	Default: No
Course categories included	<input type="text" value="Select categories"/>	Default: None
Show "All Students" option in menu	<input checked="" type="checkbox"/>	Default: Yes
Show site groups selection option	<input type="checkbox"/>	Default: No
Show grade status	<input checked="" type="checkbox"/>	Default: Yes
Passing grade to be used when course grade condition is not set	<input type="text" value="50"/>	Default: 50

The image shows a configuration page for the 'NED Mentor Manager' plugin. The page contains various settings for the block, including names, page layouts, roles, and permissions. Red annotations highlight specific settings: a red box around 'login' in the 'Page layout' field, red boxes around 'mentor-system' and 'mentor-user' in the 'Mentor role' dropdowns, and a red box around 'Select categories' in the 'Course categories included' field. Red arrows point from these boxes to their respective fields in the form.